

# Introduction

If you use Moneyworks v5 or newer, and would like to integrate it with 4D v11 or newer, then you've come to the right place! Simply download and install the component, play with the example database (or read the documentation), and you're away.

This document is based on the Moneyworks command-line documentation from Cognito (<http://cognito.co.nz/developer/cli-manual>).

The component has been tested on 4D v11r8, v12.1 and v13.4, connecting to Moneyworks v5, v6 and v7 respectively. It will operate as a trial for one hour. For a license key, or to obtain the source code, please contact us (<http://www.sussol.net/contact/>). Pricing is a simple flat rate of \$250 per year for unlimited use.

Now updated for 4D v15, including support for REST connections to versions of Moneyworks newer than v6.1 - see <http://cognito.co.nz/developer/moneyworks-datacentre-rest-api/>

Examples using the available methods are included in the accompanying example database, which also includes a form which can be used to experiment (use the **mwks\_preferences** method to open it).

## Downloads

Component (unicode) + example database for v11 is available [here](#)

Component only (without example database), with unicode switched off, for v11 is available [here](#)

Component only (without example database) for v12 (fixed for Moneyworks 7.1.9) is available [here](#) (Previous version available [here](#))

Component only (without example database) for v13 (fixed for Moneyworks 7.1.9) is available [here](#)

Component only (without example database) for v14 (fixed for Moneyworks 7.1.9) is available [here](#)

Component only (without example database) for v15 (including Moneyworks REST support) is available [here](#)

This wiki will always have the latest version of the documentation, but an older PDF version is available [here](#)

## Files and Strings

The full path must be given for any files, as the Moneyworks command line doesn't know about the Moneyworks plugins folder. Paths on the Macintosh should use the posix standard rather than the old OS9 standard. Spaces within paths may need to be escaped.

For non-REST connections, double quotes within strings should be escaped, or use Char(Double

Quote). Single quotes should also not be used (except in the *extra\_parameters* parameter in the export/import/report and form methods, which is passed verbatim to Moneyworks) as they are used internally to delimit the parameters passed to the Moneyworks command line.

## Included Methods

### mwks\_register

*(registration\_key)* → **Boolean**

Parameter	Type	Description
registration_key	String	Registration key for component

#### Return value

**True** if *registration\_key* is valid, otherwise **False**

#### Description

Registers the component using the given key string. If the key isn't valid, the component can still be used for an hour before it times out. This method should be called before attempting to use any other component method e.g. in the **On Startup** database method.

### mwks\_setup\_connection

*(p\_connect; p\_application; p\_error; connection; mwks\_location*

*[if connection=1 (Gold local): data\_path; doc\_username; doc\_pass]*

*[if connection=2 (Gold server): client\_license; doc\_username; doc\_pass; server\_ip; server\_port]*

*[if connection=3 (DC server) or 4 (DC REST server): data\_path; doc\_username; doc\_pass; server\_ip; server\_port; dc\_username; dc\_pass; dc\_os]*

*{; open\_datafile} {; xml\_output})* → **Boolean**

Parameter	Type	Description
p_connect	Pointer to string	<b>Returned</b> containing the connect string
p_application	Pointer to string	<b>Returned</b> containing the Moneyworks application string
p_error	Pointer to string	<b>Returned</b> containing the error string

connection	Integer	1=Gold local, 2=Gold server, 3=DC server, 4=DC REST server
mwks_location	String	Full path to Moneyworks executable (not needed if connection=4)
data_path	String	Full path to data file (if connection=1), or document filename (if connection=3 or 4)
doc_username	String	Username for data file (ignored if doc_pass is blank)
doc_pass	String	Password for data file (may be left blank)
client_key	String	License key for client of Gold server
server_ip	String	IP address of Gold server/DC server/DC REST server
server_port	String	If left blank, uses default port (6674 for Gold server, 6699 for DC server, 6710 for DC REST server)
dc_username	String	Username for DC or DC REST server login (may be left blank if server not running in ASP mode, otherwise it is required)
dc_pass	String	Password for DC or DC REST server (may be left blank)
dc_os	String	OS of DC server - either 'Windows' or 'Macintosh'
open_datafile	String	Optional parameter - if non blank, try to open the data file
xml_output	String	Optional parameter - if non blank, use XML output

## Return value

**True** if the connection string has been setup correctly, otherwise **False** (in which case *p\_error* is populated with the error message). If the optional *open\_datafile* parameter has been passed and is not an empty string, it will only return **True** if the data file has been opened successfully.

## Description

Sets up the necessary connection parameters for communicating with Moneyworks (*p\_connect* and *p\_application* are then used in most of the other component methods). The first five parameters are common for all connection types, and the remaining parameters depend on the connection type (three for Gold local, five for Gold server, and eight for DC or DC REST server).

The last two parameters (*open\_datafile* and *xml\_output*) are optional. If *open\_datafile* is not an empty string, it will attempt to open the data file, otherwise it will just create the connection string. If *xml\_output* is not an empty string, it will use the -x parameter to call the Moneyworks command-line (rather than -q). This gives more descriptive error messages in many cases e.g. when importing data. Note that if you use XML output, the result string will lose any tab or newline characters that you might have included in the *format* parameter e.g. when exporting data.

## mwks\_run\_command

**(connect\_string; command\_string; application\_string; p\_result; p\_error {; blob\_POST} ) → Boolean**

Parameter	Type	Description
connect_string	String	Connect string
command_string	String	Moneyworks command string
application_string	Pointer to string	Moneyworks application string

p_result	Pointer to string	For the result string
p_error	Pointer to string	For the error string
blob_POST	Blob	Optional - POST data for REST (as XML)

## Return value

**True** if successful, otherwise **False** (in which case *p\_error* is populated with the error message).

## Description

Generic method to run any Moneyworks command (used in the Execute button on the example form). The first two parameters are the connection parameters from **mwks\_setup\_connection** (*p\_connect* and *p\_application*). The result of running the command is passed back in *p\_result*. Note that for REST connections, the command must be formatted using the appropriate URL and HTTP escape characters.

## mwks\_evaluate

**(connect\_string; application\_string; p\_result; p\_error; expression) → Boolean**

Parameter	Type	Description
connect_string	String	Connect string
application_string	String	Moneyworks application string
p_result	Pointer to string	For the result string
p_error	Pointer to string	For the error string
expression	String	

From:  
<http://docs.sussol.net/> - Sussol Docs

Permanent link:  
[http://docs.sussol.net/doku.php/4d\\_moneyworks\\_component?rev=1475523092](http://docs.sussol.net/doku.php/4d_moneyworks_component?rev=1475523092)

Last update: **2016/10/03 19:31**

