# Introduction

The Moneyworks connector is a standalone application (Windows or Mac) using our Moneyworks component which is designed to periodically (or manually) export and import transactions between EDI and Moneyworks. It works in conjunction with a similar EDI connector application which generates XML files for import into Moneyworks, and processes XML files exported by Moneyworks. The basic process, which we call syncing, is:

- EDI connector generates XML orders in a specified import folder (one order per XML file)
- Moneyworks connector reads and processes XML orders from the import folder into Moneyworks
  - The EDI XML order files are pre-processed to re-format them and to split them into individual orders, each of which are imported separately
  - Orders successfully imported are moved to processed subfolder
  - $\circ\,$  Failed orders are re-tried on the next sync
  - To re-import an order which was previously imported, simply move the corresponding XML file back from the processed folder into the main import folder, and it will be included in the next sync
  - Imported orders have their flag field set to "EDI"
- Moneyworks connector checks for posted invoices in Moneyworks, having their flag set to "EDI" and which have been modified since the last successful export, and exports them as XML to a specified export folder (one XML file per invoice)
  - For each successfully exported invoice, it also generates a semaphore file in the processed subfolder, to prevent accidental re-export of the same invoice
  - If the entire export sync is successful, it updates the export timestamp (can be manually overridden if needed - see below) - otherwise the next export sync will retry and start again from the same point
- EDI connector reads and processes XML invoices from the export folder

The parameters and options for the Moneyworks connector are controlled by the *Sync* menu items:

S NeveyworksConsector	
File Edit Mode Serve Help	
Castanisation code Suns with Moneyworks Setup	
	🛛 Application 🖉 🗖 🔀
	20
	sustainable solutions
	sustainable
	solutions
	MoneyWorks' Gold

### Setting up the sync parameters

Available from the  $Sync \rightarrow Setup$  menu item. This consists of two tabs - one for the Moneyworks connection parameters, and another with settings to control the sync process.

### **Moneyworks connection**

This tab controls how the Moneyworks Connector connects to Moneyworks:

<b>b</b>		
Moneyworks connection	Settings	
Connection type	Local file (Gold)	Input
Datafile location (or filename if on Datacentre/Gold server) Moneyworks location	C:\Users\Adrian\Documents \sussol\HKSDK\HKSDK_2014_ C:\Program Files (x86) \Moneyworks Gold	<pre>evaluate expr="Today()" evaluate expr="Today()" version evaluate expr="documentpath" export table="user" export table="user" export table="Name" format="[Code]\n" export table="Name" format="[Code]\n"</pre>
Doc user name	admin	
Doc pass	******	Output
If on Gold server		
Gold client license ke	ey	
If on Datacentre/Gold se	rver	
IP addre	ss	
Port number (leav blank for defaul		
If on Datacentre		
DC user nam	e l	
DC pa	ss	· ·
Operating system of D	C Windows	Execute Cancel OK

The left hand side of the tab allows you to enter the parameters for the Moneyworks connection:

- The connection type can be Local file, Gold client, or Datacentre client.
- The datafile location or filename must be entered (full path must be entered if a local file).
- The location of the Moneyworks executable must be entered.
- Enter the document user name and password (even if blank) in all cases.
- The Gold client license key is only needed if connecting to a Gold server.
- The server IP address and port number are not needed for connecting to a local file.
- The DC user name and password should be entered (even if blank) if connecting to a Datacentre server, and the operating system of the Datacentre server must also be selected in this case.

The right hand side of the tab allows you to send commands to Moneyworks (see the Moneyworks manual for details), and you can use the examples in the *Input* drop-down menu to check that the connection is setup correctly e.g. selecting *evaluate expr="documentpath"* and then clicking on the *Execute* button should return the Moneyworks document name/path in the *Output* box (and nothing in the *Errors* box). Clicking on *OK* will save the current connection settings, and *Cancel* will discard any changes made.

#### Settings

This tab controls the sync process itself:

<b>b</b>				
Moneyworks connection Settings				
Import sync timestamp	2015-07-20 20:59:43			
Export sync timestamp	2015-07-21 12:25:44			
Invoices folder for export	X:\N\export\	Choose		
Orders folder for import	X:\N\import\	Choose		
Email address for notifications	edi@hksdk.com			
Import sync interval (minutes)	60			
Export every X syncs	1			
Export colour	None 🔻			
Re-export colour	Red ▼ None Orange Red Magenta Cyan Blue Green Brown		Cancel	ОК

- The *Import sync timestamp* field is for information, and is updated after every successful import (even if some orders fail to import however, these will be re-tried next time)
- Only invoices which have been modified in Moneyworks after *Export sync timestamp* are exported from Moneyworks this field can be manually edited if needed, and is updated after every successful export
  - By default, an invoice can only be exported once, and only after being posted and only if its flag field is set to "EDI"
  - If *Export colour* is set to a value other than "None", then there is an additional restriction so that only invoices with that colour can be exported
  - To force re-export of an invoice, specify the *Re-export colour* and set the invoice colour to that colour
- The import and export folders must be specified using *Import folder for orders* and *Export folder for invoices*
- To receive email notifications of any errors written to the log file, enter a valid email address in the *Email address for notifications* field
- If the *Import sync interval* is set to any value other than zero, the connector will automatically attempt to perform a sync every X minutes
  - $\circ\,$  In this case, error messages are redirected to the log file (in the Logs folder) instead of popping up on the screen
  - By default, *Export every X syncs* is set to 1 so that an export sync is done every time, but that can be edited so that exports run less frequently e.g. if set to 24 and with a sync interval of 60 minutes, imports will run approximately every hour, but exports will only run approximately once a day

# **Initial Setup of Moneyworks Datafile**

- Make sure that the item codes in Moneyworks match those in EDI: the GTIN code in EDI corresponds to Product.Barcode in Moneyworks
- Make sure that the customer codes in Moneyworks match those in EDI: the GLN/EAN code in EDI corresponds to name.custom1 in Moneyworks
- Make sure that there are open periods in Moneyworks for all of the transactions that you want to import from EDI.
- Make sure that the base currency in Moneyworks has been set correctly.
- Make sure that the tax codes in Moneyworks have been setup correctly, with the same rates as in EDI.

## **Common Errors**

- No period has been opened in Moneyworks for a new transaction
- If you're connecting to a local datafile, make sure it isn't already open in Moneyworks
- Mismatch between the item/customer codes in Moneyworks and those in EDI

### Troubleshooting

1. Check log file created for each sync in the *Database/Logs* folder.

From: http://docs.sussol.net/ - **Sussol Docs** 

Permanent link: http://docs.sussol.net/doku.php/moneyworks:hksdk\_connector?rev=1437571387



Last update: 2015/07/22 13:23